

Downloading & Transferring eBooks

Initial Setup

If you are using a Barnes & Noble Nook, Sony Reader, Kobo, Literati, Pandigital Novel or other dedicated e-reader you will need to do the following before checking out eBooks.

1. **Download and install Adobe Digital Editions (ADE) on your computer.**

To check out eBooks and read them on your e-reader (or home computer), you must install the free software program [Adobe Digital Editions](#). This program manages the eBooks you have borrowed and lets you read and transfer eBooks to an e-reader. On the ADE website, scroll down and click the “Launch” button to download and install the software.

2. **Create an Adobe ID and authorize your computer.**

In order to transfer your downloaded eBooks to your e-reader, you will need to **create a free** Adobe user ID. After ADE has installed, a setup assistant will appear and prompt you to authorize your computer by logging in with an Adobe ID. To create an Adobe ID, click “get an Adobe ID online” in the setup assistant window.

Note: If you choose “Don’t Authorize Computer,” you can still download eBooks from the library and read them on your computer, but you will not be able to transfer them to your e-reader.

3. **Activate your e-reader.**

Connect the [compatible e-reader](#) to your computer and open the Adobe Digital Editions program. ADE should detect the e-reader and a "Device Setup Assistant" window will display. Click "Authorize Device." The program will activate the e-reader which will allow you to transfer DRM-protected eBooks to the device.

Note: Adobe Digital Editions and the e-reader must be activated with the same Adobe ID to transfer DRM-protected eBooks to the device.

Checking out and Downloading an eBook

The OverDrive catalog (<http://overdrive.dbrl.org>) is where you can search and download [eBooks](#) and [audiobooks](#). You can click on one of the collection links to the right (under eBook Fiction or eBook Nonfiction), or browse the featured eBooks collection near the top of the catalog.

1. Once you have found an eBook to check out, click the “Add to cart” link, then click “Proceed to Checkout.”
2. Enter your library card number and PIN (by default, your birth date in the format MMDDYYYY).
3. Click “Confirm check out” and then click the “Download” button under each eBook.
4. In the pop-up window that appears, select “Open with: Adobe Digital Editions.”
5. Adobe Digital Editions will open on your computer and begin downloading the eBook.

Note: If you accidentally chose “Save File” instead of “Open with” when downloading the book, you can manually click and drag the eBook to Adobe Digital Editions or select “Add Item to Library” under the ADE “Library” menu.

Tip: You can return the eBook to the library manually via the pop-up menu in the upper-left-hand corner of the book.

Transferring eBooks to an E-reader Using Adobe Digital Editions

1. Once you've downloaded the eBook, plug your e-reader into your computer.
2. Click the Library View icon (three book spines) in ADE. Your e-reader should appear on the left-hand side.
3. Select the eBook and drag it to your e-reader.
4. Disconnect your e-reader by ejecting it safely from your computer.
5. Follow the device instructions to locate and read the eBook.

Note: For the Nook, you should be able to find the eBook in Library > My Files > Digital Editions or Documents.

Taken from the Daniel Boone Regional Library Web Site (<http://www.dbri.org/ebooks/download-transfer-ebooks>)